

## NethServer 6 - Feature #1626

### Load CUPS printers

01/16/2013 04:28 PM - Giacomo Sanchiotti

|  |                  |                    |            |
|--|------------------|--------------------|------------|
| <b>Status:</b>   | CLOSED           | <b>Start date:</b> | 01/16/2013 |
| <b>Priority:</b>   | Normal           | <b>Due date:</b>   | 02/28/2013 |
| <b>Assignee:</b>   |                  | <b>% Done:</b>     | 100%       |
| <b>Category:</b>   | nethserver-samba |                    |            |
| <b>Target version:</b>   | v6.4-alpha2      |                    |            |
| <b>Resolution:</b>   |                  | <b>NEEDINFO:</b>   |            |
| <b>Description</b>   |                  |                    |            |
| Add template fragment to /etc/samba/smb.conf template for printer automatic loading from CUPS.   |                  |                    |            |
| Add an option in web UI to enable/disable CUPS integration.  |                  |                    |            |
| <pre>load printers = yes {   my \$useCups = \$smb{'UseCups'}    'disabled';   if (\$useCups eq 'enabled') {     \$OUT.="printing = cups\n";     \$OUT.="printcap name = cups\n";   } }  [printers] comment = All Printers path = /var/spool/samba browseable = no guest ok = no writable = no printable = yes {   \$OUT .= "use client driver = ";   \$OUT .= \$smb{UseClientDriver}    "yes"; }</pre> |                  |                    |            |

#### Associated revisions

##### Revision aaab9730 - 01/16/2013 04:31 PM - Giacomo Sanchiotti

createlinks, smb.conf: move samba configuration to nethserver-samba package. Refs #1626

##### Revision 92ff305f - 02/20/2013 06:00 PM - Giacomo Sanchiotti

smb.conf template: add CUPS integration. Refs #1626

##### Revision d05066b9 - 02/21/2013 11:52 AM - Giacomo Sanchiotti

createlinks: expand ssl crt and key on nethserver-cups-update event. Refs #1626

## History

---

**#1 - 01/24/2013 03:52 PM - Davide Principi**

- *Target version set to v6.4-alpha2*

**#3 - 02/07/2013 06:46 PM - Davide Principi**

- *Project changed from 2 to NethServer 6*

**#4 - 02/21/2013 03:02 PM - Giacomo Sanchietti**

- *Status changed from NEW to MODIFIED*

Implemented using UseCups property.

UseCups can be enabled or disabled. Default is enabled.

For now there's no need to expose this prop in the UI.

**#5 - 02/27/2013 06:22 PM - Davide Principi**

- *Assignee set to Giacomo Sanchietti*

**#6 - 02/28/2013 04:22 PM - Davide Principi**

- *% Done changed from 0 to 100*

**#7 - 03/21/2013 04:17 PM - Davide Principi**

- *Status changed from MODIFIED to CLOSED*

**#8 - 03/21/2013 04:18 PM - Davide Principi**

State set to closed on NethServer 6.4 alpha2 release